

Track plans for N, TT, HO, S, and O scale model railroads
























- Electronic





























#### Whether you're a beginner or a seasoned modeler, you'll discover that these books add to the enjoyment you get from your hobby. Select the books you need and buy them today.

to building benchwork and roadbed. 56 pages, 202 illustrations \$5.95
How to Operate Your Model Railroad—The definitive guide to model railroading fun through operation. 335 illustrations in 184 pages\$13.95
Small Railroads You Can Build—This all-new second edition features four layout projects for the beginner, all packed into 48 pages
Scratchbuilding & Kitbashing Model Railroad Stations—Build a variety of model stations as you're guided by 100 color-packed pages\$4.95
Classic Articles from MODEL RAILROADER—Here's a book that captures the tradition of model railroading with timeless articles\$4.50
Creative Layout Design—John Armstrong's complete guide to fitting a layout to your needs. 124 pages, over 200 illustrations\$11.95
Track Planning for Realistic Operation—A new, updated edition provides hundreds of track planning ideas
How to Wire Your Model Railroad—Easy wiring for the beginner and advanced material for the expert, covered with text and diagrams\$7.50
N Scale Primer—A great guide for the modeler in N scale railroading. Two complete layouts described, plus all the basics
Scenery for Model Railroads—The best methods, explained with photos (several in color) and drawings. Includes hard-shell techniques \$7.95
Building an HO Model Railroad with Personality—In 68 pages, learn how to build the 4' x 8' Jerome & Southwestern
N Scale Model Railroad Track Plans—Over 60 complete layouts for anyone working in N. Scenery ideas and track brands are covered
Track Plans for Sectional Track—Contains 144 track plans by Linn West- cott and includes lists of pieces of track needed for each layout \$4.50
18 Tailor-Made Model Railroad Track Plans—Expert track planner John Armstrong provides 18 dream model railroads. 80 pages
101 Track Plans for Model Railroaders—Here's how to choose your track plan, how to build it, and how to change it to fit your needs
How to Build Realistic Model Railroad Scenery—In 100 pages, this title shows you a new, sure-fire way to build excellent scenery every time. \$8.50
Easy-to-Build Model Railroad Structures—A collection of plans from which you can build a variety of attractive scale buildings\$4.50
Model Railroading with John Allen-More than 200 photos fill 144 large- format pages, re-creating John Allen's legendary Gorre & Daphetid. \$23.95
The ABC's of Model Railroading—A wonderful guide for the beginner to learn the basics of model railroading. 70 pages, 175 illustrations \$6.75
Traction Guidebook for Model Railroaders—For the avid traction fan or beginner; shows you the intricacies of interurban modeling
HO Railroad That Grows—Start on a sheet of plywood, and in 8 easy steps you have a complete 4' x 8' HO scale model railroad
Track Planning Ideas from MODEL RAILROADER—Selected from over 20 years of MR, here are 58 imaginative, useful track plans
HO Narrow Gauge Railroad You Can Build—Join Malcolm Furlow and build the marvelous HOn3 San Juan Central\$7.95
Practical Electronic Projects for Model Railroaders—All phases of electronic model railroading, throttles, lighting, sound
34 New Electronic Projects for Model Railroaders—Here are 34 challenging electronic projects for beginners and experts. 80 pages\$10.95
All Aboard: The Practical Guide to HO Model Railroading—This new book introduces the hobby and answers beginner's modeling questions \$6.95

#### KALMBACH BOOKS.

1027 NORTH SEVENTH STREET, MILWAUKEE, WI 53233







© Kalmbach Publishing Co.

direct, include postage and handling: U.S., \$1, foreign \$1.50. Wisconsin residents add 5 per cent sales tax.

Prices subject to change. When ordering

#### BOSTON PUBLIC LIBRARY.

MAY 1989

## 101 TRACK PLANS FOR MODEL RAILROADERS

BY LINN H. WESTCOTT

#### CONTENTS

#### **PLANS**

Railroads for very small table	es	•		•	*		-	2
Small shelf railroads -	-	. ]						6
Small table railroads -	-	. 1				6.T.S.		10
Railroads for 4 x 8 tables			-		-	19-5		14
Railroads to 6 x 10	-	2				-		18
Railroads up to 9 x 12 -			-	•			•	22
Railroads for 12 x 16 spaces				•		-	•	33
Trolley layouts				-				42
Larger shelf railroads -	٠					-		45
Railroads for a single garage	•		-	-			-	48
Railroads for large spaces			-	-	1/2	•	4, 8,	57
Plan index	20	•	-	2	-	**	-	70
OTHER FEATURES								
How to choose your track pla	n				7	100		3
How to build your railroad fro	om p	olans				-		5
How to change plans to suit yo	our r	needs			*			9
If I had a million	-	-	10	-	192	200		60

#### KALMBACH BOOKS

© 1956 by Kalmbach Publishing Co. All rights reserved. This book may not be reproduced in part or in whole without written permission from the publisher, except in the case of brief quotations used in reviews. Published by Kalmbach Publishing Co., 1027 North Seventh Street, Milwaukee, WI 53233. Printed in U. S. A. ISBN: 0-89024-512-6.

First printing, 1956. Second printing, 1957. Third printing, 1961. Fourth printing, 1963. Fifth printing, 1967. Sixth printing, 1969. Seventh printing, 1970. Eighth printing, 1972. Ninth printing, 1974. Tenth printing, 1975. Eleventh printing, 1976. Twelfth printing, 1978. Thirteenth printing, 1980. Fourteenth printing, 1982. Fifteenth printing, 1984. Sixteenth printing, 1987.

Each of these track plans is an adventure in itself, like a visit to another model railroader's home railroad. Each plan is built around some railroad theme with an atmosphere of real, or sometimes imaginary, countryside. Almost every plan offers you ideas that you can use on any model railroad — which makes this book far more useful and more interesting to browse through than one might expect of a collection of track plans.

#### Easy to use

The plans are arranged mostly by size, starting with railroads for the smallest tabletops and ending with club-sized and deluxe railroads. Simple steps are given in the text to help you:

- 1. Choose the best plan.
- 2. Modify it if desired.
- 3. Build the railroad.

Literally thousands of scale model railroads have been built from plans by Linn Westcott, and he has included examples of his most popular railroad ideas along with some of the best work of other expert track planners. Many of these plans have never appeared elsewhere and others are completely revised from the most popular plans of the past.



#### 1. Stockton & Darlington RR. Very sharp curves

Even a very small railroad can have a yard by folding it around the outside of the oval. Streets are built at an angle deliberately to get the effect of more space. Keep buildings small but with plenty of detail.



# ADAMS WESLEY WESLEY ADAMS Downwy trock Of future awarenion Of

#### What scale do you build?

#### N SCALE

The plans in this book were prepared before N scale was developed. However, you can reduce any plan to suit N scale needs by following the dimensions given in the tables. Remember, though, that any aisleways running into the table space must be maintained wide enough for you to walk conveniently. You have great freedom in planning with N scale. The ruled lines on all plans are 6" apart.

#### TT SCALE

You're lucky, because no matter what the size of your railroad room, you have a wide choice of plans that will fit it. The ruled lines across all plans are 9" apart for you. Such dimensions as elevations, turntable diameters and special radii (but not angles) should be multiplied by 3/4" to get the correct figure for your use. Read the text and you'll find other suggestions that will help you.

#### HO SCALE

The ruled lines across all plans are 1 foot apart. Other dimensions such as radii, elevations, etc., are shown in inches for your use. Many of these railroads were originally built in the HO size. Be sure to read the text for other ideas and helpful kinks.

#### S SCALE

Your scale is a good compromise between space and construction detail, and many of these plans take advantage of both. The ruled lines across all plans are spaced 18" apart for your use. Add half again to the printed dimensions shown for elevations, radii, turntables, etc., to obtain your correct size. Angles remain unchanged. On some large plans you may want to cut an extra opening or two through the scenery so you won't have to reach too far from the edge of a table to reach critical switchwork. Read the text for more suggestions in layout and scenic construction.

#### O SCALE


The ruled lines across all plans are spaced 2 feet apart for your use. Elevations, turntable diameters, special radii and other figured dimensions on the plans should be doubled for your use. Angles remain unchanged. Many of these plans were originally built in O gauge, but in some you'll find that the reach from the edge of the table to critical trackwork may be a little far. The remedy is the same as we suggested for S gaugers: cut a small access hatch through the scenery.

#### Railroads for very small tables

See page 70 for more data.

#### 2. Kettle Hills & Eastern RR. Very sharp curves

Two-level operation is one way to get the effect of a larger railroad into a small space.



#### 3. Bay State Western Ry. (At left.) Sharp curves

A double-track railroad needs at least one crossover, preferably two. To save space, one switch of each crossover is flopped from the usual position so that it can extend into the curve. This is always a good trick in track planning.

#### 4. Reddy River & Piedras RR. (Opposite page.) Sharp curves

This railroad can handle two trains, or you can switch one while another runs. Originally this was just a sketch in Model RailROADER magazine but it has so many good points that we've figured it more carefully for your use.

### How to choose your track plan

THE first step in choosing a plan in this book is to discard all the layouts that are too big for the space you have. The plans are arranged, for the most part, in groups of gradually increasing size; you can find all sizes compared in the index on page 70. Later on I'll show you how plans can be adjusted to the exact size and shape of your table or room. After you have narrowed the selection to those plans which will fit your space, the choice depends on what you like.

While searching through the book for plans, turn the pages upside down, then to the right or left. Look at all the plans in a mirror, too. In this way you won't overlook any plan that's well suited to your space.

#### What plan would I choose if I wanted a good average layout?

Look for a plan with one- or twolap main lines. If space allows, these should have return loops in each direction so trains can be turned to go clockwise or counterclockwise for more variety of operation. An average layout should have some space for scenery, but if the area is small, getting in enough track is usually more of a problem.

Selected one-lop and two-lap ovals:
1, 3, 4, 16, 18, 19, 20, 22, 23, 25, 29, 36, 38, 46, 56, 60, 74, 79.
Selected plans with one return track:
13, 27, 42, 50, 61.
Selected plans with two return tracks:
24, 53, 54, 57, 58, 59, 65, 77, 84, 100.

#### What kind of plan is best for switching?


It doesn't matter much how the main line goes as long as you have yards and industrial spurs in good supply. Take any plan in this book and add more spurs and yards if there aren't already enough. If you prefer way-freight operation, pick a plan with a long main line with spurs frequently turning off in every direction. If you prefer yard switching, keep the main line more simple and choose a plan that allows for many yard tracks.

Railroads featuring switching: 3, 4, 6, 7, 8, 9, 10, 11, 12, 18, 20, 23, 24, 25, 26, 27, 33, and most plans from 38 anward. Bold face indicates plans where switching in the yard doesn't have to interfere with mainline running.

#### What plans are best for railroadlike train operation?

The essence of railroad train operation is to make up a train in the yard and then send it over the main line (or perhaps a branch) to another yard or terminal. This is called point-to-point operation by model railroaders, but you don't necessarily require a point-to-point plan to accomplish it. Any plan with a main line of some length can be used if the terminals are arranged well. You can connect two terminals into any oval so that a train must use most of the oval main line

when going from one terminal to the other, like this:



By using a loop for one terminal, you'll usually have more space to build a bigger yard at the main terminal. Notice how this was done in plan 100. The wye allows trains to enter the two-lap oval going either way. After passing the wye, a train is forced to stay on the main line all the way around. There are no short cuts as they wouldn't improve operation.

The train reaches a terminal only after completely circuiting the main line. In this plan the train has a choice of terminals: it can go back into the original yard (as though it had reached a different city), or it can terminate in one of the return loops — Little Miami Loop or Barberton Cutoff. From these it is immediately ready to make another trip over the main line in the opposite direction.

The point is that it's nice to have an oval type of plan for test and display runs, but an oval can also be arranged for railroadlike point-to-point operation as well. For most men a plan that combines both kinds of operation is more satisfying.

Pure point-to-point plans have a simplicity and charm of their own, especially if track never doubles back on itself. I think you'll see this better than I can explain in words if you look over several point-to-point plans.

Point-to-point roilroods:

5, 8, 10, 40, 43, 44, 45, 47, 51, 55, 68, 69, 72, 73, 75, 78, 81, 83, 87, 94, 95, 96, 101. Bold numbers are loop-to-loop plans.

Roilroads suited to both point-to-point and avaltype running:


9, 17, 18, 24, 26, 27, 28, 34, 35, 42, 48, 50, 53, 54, 59, 61, 62, 63, 65, 66, 67, 70, 72, 73, 77, 82, 84, 86, 88, 89, 90, 92, 93, 97, 98, 99, 100. Plans 64 and 76 are out-and-back type.


#### What kind of plans are most suited to running two or more trains at once?

On most plans, you can run one train on the main line while another is switched in the yards. Sometimes provision can be made so the two never interfere.

A two-track main line is obviously suited to running two or more trains. Put one on each track and just let

(Continued on next page)





#### Are some plans better for the man who wants signaling or all-automatic control?

Kennedy-Wyradoorbell

EDWOOD PT

Lumber RR.

Some of our plans are especially prepared with signaling in mind.

Railroads most suited to signal installation: 9, 19, 24, 31, 38, 40, 41, 46, 49, 50, 53, 54, 56, 57, 58, 59, 60, 61, 62, 65, 73, 74, 76, 77, 79, 80, 82, 85, 86, 91, 92, 94, 97, 98, 100. Those shown in bold are easier to adapt for ATC olong with plans 15 and 29.

Of course, you can add signals or automatic control to any plan, but the electric circuits are much simpler on one-way track such as you'll find where most or all of a railroad is double-tracked.

#### Wouldn't a plan with a doubletrack main line be better than one with single track?

If you like fast-running, heavy traffic, or if you want to run two trains with a minimum of control-panel equipment, double track has the advantage. But usually single track is the better choice. It offers more operating fun per train because you have more to do.


Also, scenic effects are easier to work out on a single-track type of plan. The track is narrower so it leaves more space for scenery, but the most important reason is that narrow track looks much longer. Your whole railroad may look half again as big with single track as with double.

#### What plans are the best for scenic effects?

Look for plans with ample space between track routes and plenty of space between the track and the table edges. Usually a simple track arrangement is most satisfactory, but where you can make the scene look logical, several routes can be run through the same part of a scene. Layouts with grades and curves make more interesting scenery than straight level lines.

Den't overrate the importance of scenery in choosing a plan. You can

Continued on page 19



#### How to build your railroad from plans

Pentry, track laying, and scenery construction, you'll find that you have a choice between "flat top" and "grid" (open top) types of table construction. In a nutshell, the type of table with a flat plywood sheet for a top saves a little time in construction providing you build a one-level type of railroad. The open or grid type of construction is better for scenic reasons, but may take a little longer to build. On a multilevel railroad, grid construction undoubtedly saves time.

All plans can be built by grid methods.

#### How do I transfer track locations from the printed plans to the railroad framework?

Our plans have lines ruled across them each way in uniform spacing. The spacing represents:

6" for N scale construction. 9" for TT scale construction. 12" for HO scale construction. 18" for S scale construction. 24" for O scale construction.

If you draw these same lines across the top of your framework or plywood surface, you can estimate how many inches any feature is from the nearest lines and transfer this location from the plan to the corresponding lines on the railroad table. For greater accuracy, measure the scale inches from the nearest lines on the plan.

We've printed scales on the margins of our index pages for your convenience. Many of the plans are drawn in ¾", ¾s", or ¾6" scale. You'll find an ordinary ruler has the desired six or 12 marks per square on the plan for measuring anything that falls between lines.

#### Isn't it a good idea to work from large plans?

Large plans are better if you plan to make changes of your own. But otherwise you should get along fine with plans just as they come in this book. This is because so few dimensions on a track plan are really critical. We don't ordinarily permit persons to copy plans from our publications without written consent. However, you have our permission to get an enlarged copy made of any plan if it is for building your own personal home railroad. Photocopy firms in the nearest city are well equipped to do this for two or three dollars.

It's also easy to enlarge plans by drawing lines 1½", 2", or 3" apart each way on a piece of paper. Then you copy the location of track one square at a time, enlarging it by hand from the squares on the plans in the book. This may sound tedious, but it isn't as bad as you might expect. Usually freehand work will be accurate enough, but double check the locations of curve centers and switch ladders for safety.

#### What parts of the track should be located carefully?

The curves near the corners of a table often have a critical location. Ladder tracks in yards should also be arranged accurately or else there may not be enough room for all the switches. Where tracks are closely parallel, be sure tracks are separated enough so cars on one track won't sideswipe engines or cars on the other. Here are the minimum distances to maintain between track centers for various curves:


Sharp curves	Conventional curves	Broad curves
174	178	1
17/8"	111/16"	115"
21/2"	21/4"	2"
334"	336"	3"
5"	41/2"	4"
	11/4" 17/8" 21/2" 33/4"	$\begin{array}{ccc} \text{curves} & \text{curves} \\ 1\frac{1}{4}" & 1\frac{1}{8}" \\ 1\frac{7}{8}" & 1^{11}/16" \\ 2\frac{1}{2}" & 2^{1}4" \\ 3\frac{3}{4}" & 3\frac{3}{8}" \end{array}$


Straight tracks can be as close as 13 scale feet from center to center, and this looks very realistic. However, our plans and most builders use the separation shown above for broad curves for straight track as well.

We used this same distance as the clearance from track to edge of table or wall in most of our plans. If you have difficulty making things fit, you can cut this in half. You might encounter such a difficulty if the switches you use are longer than NMRA size, as they frequently are. More about this later.

#### Can I use sectional track to build from these plans?

Yes, but you'll have to cut many short pieces of straight and curved





Continued from page 5

track because only rarely will a plan have track that matches an even number of pieces of sectional track.

If you have a little more space than needed, you won't need as many short sections of track. You can paraphrase the plan, build the same track arrangement but let the dimensions yield to the units of the track sections.

#### Is there any particular order for locating track lines on the tables?

Definitely yes. Unless you have lots of extra space, it would be asking for trouble to start locating track at the yard and work around the main line to the other end of the railroad. You'll avoid a good many pitfalls if you work this way instead:


1. Locate all curves that swing near the outer corners of your space. You can make a cardboard template to the correct radius and use it like a curved ruler. (Another way is to use a string or wooden boom and swing a pencil from the curve center.) Draw the curve beyond each end for a ways.

 Locate other curves in the same way. Don't worry about straight tracks between curves yet.

3. Locate the main and ladder tracks of your yard. Sometimes they're the same track.

4. Add connecting tracks everywhere. Usually these will be straight, but often you can get a beautiful effect by using a gradual curve with little or no straight track even in places where the plans show straight track. Plan 49 has these sweeping curves in place of straight track. Plan 50 also has a few.

5. Where connecting tracks include track switches, locate the straight track first. Then locate the branch as a straight line at the proper angle. The angle is 1" in 4" for a No. 4 switch (14¼ degrees) or 1" in 6" for a No. 6 switch (9½ degrees).



6. Wherever these lines cross is called the P.I. (point of intersection) of the switch, and using the P.I. is the best way to locate a switch. From the P.I. you mark off a distance obtained by multiplying the switch number by the gauge to find the place where the frog of the switch will come. Do not use the point end of a switch for measurements as it varies with different manufacturers.

Here are the P.I.-to-frog distances for switch location figured for you:

TOT	SAATERIT	incation inguica to	Jour
Scale		P.I.F. for No. 4	P.I.F. for No. 6
N		15/16"	131/32"
TT		17/8"	213/16"
HO		25%"	315/16"
S		3½"	51/4"
0		5"	71/2"
13 TO THE LAND			A

Our plans show marks for the switch frog and point with fine crossties. However, it is better to use the P.I.F. method for locating switches than to measure them off from plans; fewer errors will occur and those you do make will tend to be self-compensating.

#### How do I use the printed dimensions, say for O gauge? Other gauges?

Track elevations, minimum radii and other dimensions, are printed directly on our plans and captions. Multiply these figures by:

1/2" for N scale railroads.
1" for TT scale railroads.
1" for HO scale railroads.
11/2" for S scale railroads.
2" for O scale railroads.

Do not multiply angles as they are the same in all scales. Switch sizes are also angles, so they're the same in every scale too.

#### What size are the switches on the plans?

Except where noted, No. 4 switches are used with sharp curves, No. 6 with all others. Very sharp curves marked 15" or 16" radius can be used with No. 4 turnouts as well, but usually special switches or stub switches that have a curve right through the entire switch are used. You usually have to build these yourself.

What is a stub switch? It's like an ordinary switch at the frog end except that there may be a curve through the frog. However, at the point end the approach rails are swung from one branch to the other like the end of a turntable. Stub switches were common on railroads years ago and are still found on old track. Their advantage is that they allow a sharp curve to run right through the switch gracefully, and they have an "old-time" look.

#### What if I can't get as many switches into the space as you show on the plan?

This can happen, especially at the throat of a yard or between several crossovers. We used NMRA (National Model Railroad Association) switch dimensions for our plans. But commercially made switches are sometimes made extra long. The distance from point to frog is not only too long, but there also may be an inch or more of straight track in front of the points.

In most places you won't notice this, but if switchwork is tight, feel perfectly safe in either bending the point end of a switch into the adjoining curve or in actually shortening the switch and even the switch points. The length from point to frog can be as little as 1½ times the P.I.F. listed in the last answer.

#### What are the curve radii used in the plans?

Plans are classed with sharp, conventional, or broad curves in the index on page 70. Here are the minimum radii we used for each class:

Scale	Sharp	Conventional	Broad
N	9"	12"	15"
TT	131/2"	18"	221/2"
HO	18"	24"	30"
S	27"	36"	45"
0	36"	48"	60"
Turnout size:	4	6	6

Where there's a second track around the curve it will either have a different center or else the following radius is used from the same center.

Scale	Sharp	Conventional	Broad
N	101/4"	131/8"	16"
TT	153/8"	1911/16"	24"
HO	201/2"	261/4"	32"
S	30¾"	393/8"	48"
0	41"	521/2"	64"

### How can I follow your recommendations for radii of 261/4" in HO, etc., when track is made in 26" radius instead?

Engines and cars will sideswipe when only 2" separation is used in HO between curves of 24" and 26" radii. The problem is similar in O gauge, S, TT, and N. Even the 2\frac{1}{4}" separation we recommend for HO isn't enough for some articulateds and other long engines.


The answer is to spring the commercial radius track out enough so it follows the slightly wider recommended radius line. Notice that the second track paralleling an 18" radius track in our plans is given as 20½", while commercial track comes in 20" or 21" instead. Here, if you cannot spring the 20" track, you can add ½" of straight track at each end of a 90° curve; 1" in the end of an oval, etc.

#### How do I use the track elevations shown on the plans?

First, multiply all the elevations shown to convert them to your scale. If you work in N, multiply by ½"; in TT, by ¾". In HO the elevations are already correct. In S, add half again; and in O, double the elevations.

Now locate the part of the plan showing zero elevation at any chosen height from the floor or table top. Use a carpenter's level to transfer this zero to other parts of the railroad, then add the elevations you calculated for any point.

Between the places where we've



Continued from page 7

shown elevations, keep the grade rising or falling evenly. At the places where we've shown elevation figures, the grade usually changes. It may be to a steeper grade or it may be a summit or sag. In any case, bend the change of grade gradually over a car length or more of distance. We've tried to arrange elevations so you won't have to have any of these "vertical curves" running through a track switch.

Small arrows next to the elevation dots always point upgrade. If the point is a summit, the arrowhead just touches the dotted line, rather than crossing it. At the foot of a grade, the other end of the arrow touches the dots.

#### Is there plenty of clearance for building bridges?

We've used a separation of 29 scale feet from base of rail to base of rail as the separation of one track above another. This is 2" in N, 3" in TT, 4" in HO, 6" in S, and 8" in O.


This should give you enough clearance to build a roadway with plenty of room above the lower track. Later you can saw out the roadway and build the bridge.

In a few places, tighter clearances (less than 4" in HO) are indicated on the plan. In these tight places you'll need thinner support for the upper track. The clearance from lower rail top to the underside of a bridge must be at least:

1½" in N scale. 2½" in TT scale. 3" in HO scale. 4½" in S scale. 5½" in O scale.

#### Must I cut gaps in the rails exactly where you show them?

You can cut them anywhere within half a car length or so of where we show gaps, and it doesn't matter whether gaps are opposite or staggered. To move a gap farther might



### How to change plans to suit your needs

WHEN your railroad space isn't the same size and shape as the plan you like, you can still adjust the plan to make the best use of the space. You may want to change a plan for other reasons too, such as to borrow the yard from one plan for use in another.

Even if you're not sure you need changes, it's good to think about them. Think about each suggestion we make with respect to your own plan, and listen to comments of friends, too. One change that sometimes helps is to make the high tracks low and the low tracks high, a sort of inverting. (You can do this safely by subtracting each elevation on a plan from the highest elevation shown.) This trick can put a troublesome track under the yard instead of over it, or it may raise some


part of the railroad to clear a pump or some other obstruction in your basement.

The yards and terminals in our plans are usually located where they can make the most use of the space, or else where we thought you could get at them easily for operating. But if a wall or some other feature makes

Continued on page 38


#### Small railroads

All plans to same scale.



10. Pittsburgh, Midvale & Ironton RR. Very sharp curve


Doubling back the main line gives the effect of a train going somewhere after it completes its yard switching. To build this in the space shown, a 15" radius curve must be used. This kind of plan is easy to combine into a bigger railroad you might build someday.



Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.


#### 11. Logan Street Yard. Conventional curves


You can operate this small corner-type yard just as it is, but if you have a longer space, extend the track to the left. You can put a lot of superdetail into a plan like this. The conventional curves will handle any loco.




#### 12. Mechanic Street Yard. Conventional curves

This yard also uses conventional curves and No. 6 switches, so that if you make it a part of a large layout later, you can handle any length of locomotive. The trackwork is made particularly complicated for so small a yard in order to make both construction and operation more interesting.








#### 13. Elizabeth & Rahway River Ry. Sharp curves


This type of railroad is easy to put together and lends itself well for window displays, portable table railroads and beginner's projects.



#### 14. Blue Valley RR. Sharp curves


Figure-eight plans don't look quite as toylike as a simple oval, but either can be vastly improved by good scenery. Here's one of those rarities where one bridge is built above another.

Multiply figured dimensions and elevations by: 1/2" for N %" for TT 1" for HO 11/2" for S 2" for O Crossing angle is the same in all scales.




15. Lake District Ry. Adapted from a design by W. R. Budd. Sharp curves

This railroad won a prize in a contest for small railroad plans. We've modified it to use standard sizes of switches. Curves are sharp. The three laps are cleverly arranged to give a long run.




# 16. Valley Central Lines. Very sharp and sharp curves

This railroad is similar to plan 3, but it isn't as wide. This is accomplished by using very sharp curves, 15" radius, for the inner passing tracks. The remaining curves are the usual 18" radius for this type of plan and turnouts are No. 4.




# 7. Gorre & Daphetid. By John Allen. Very sharp curves


This name identifies the beginning of what has since become one of the most complicated but finest home model railroads ever built. We've changed the eurves to 15" and larger radii; originally they were even sharper. Turnouts are No. 4.



# 18. Turtle River Industrial District. Sharp curves


Scenery and structures will look good on a plan like this. This type of plan is excellent for the man who wants a good effect without complication.





## Sharp curves 20. New Industry Connecting RR.

Compare this one with plan 18. Here scenery is sacrificed for much more track. There are not each place. many more places to switch, but there is more car and engine capacity at each p plan for the fellow who builds lots of cars but has only a small space for his railroad. but there is more car and engine capacity at




curves Sharp Salt Range RR. 00 Tonopah 22.

Unless there's a mine working somewhere out on the desert, a line like this is likely to fold up anytime. Put trees and grass over the same reddish earth and it will be like an entirely new railroad — might even fool folks at first.



# 21. Rockport & Oyster Bay RR. Sharp curves

Scenery at the waterfront is the main feature of this otherwise very simple railroad plan.



Multiply figured dimensions and elevations by: %2" for N %2" for TT I" for HO 11%" for S 2" for O

All plans have turnouts.

# 23. Columbia & Cascade RR. Sharp curves


Ruled lines across plan are:
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O

See page 70 for more data.

railroad. The peculiar placement of the passing For two-train operation, this is a most compact tracks can be used to save space on other plans.


#### WOODSTOCK + (2) DUNDAS LONDON INGERSOLL HAMILTON BRANTFORD JC ST THOMAS 214 DES JARDINS 2. (519) 21/23

24. Toronto, Hamilton & Detroit RR. Sharp curves



25. Mohawk Southern Ry. Sharp curves

#### 26. Pennsylvania & Potomac RR. By John Armstrong. Sharp curves



### Railroad

Multiply figured dimensions and elevations by

%" for N %" for TT 1" for HO 1%" for S 2" for O

all scales.


Crossing angle is the same

Ruled lines across plan are: 6" apart in N 9" apart in TT 12" apart in HO


24" apart in O See page 70 for more data.

18" apart in S

#### for tables





27. Tremont & Cambridge RR. Sharp curves




28. Rock Island & Moline Belt Line. By Mark Canum. Sharp curves


#### 29. Nantahala & Smoky Mountain Gorge RR. Sharp curves








30. Lime Ridge, Hercules & Portland RR. By Bill Wight. Very sharp curves



31. Jersey Valley Central RR. By Bill Wight. Very sharp curves

32. Custer & Front Range RR. By Bill Wight. Very sharp curves





Multiply figured dimensions and elevations by:

tions by:

½" for N

¾" for TT

1" for HO

1½" for S

2" for O

Exception:
Elevations in plan


34 are in scale feet
for your scale.

Crossing angle is the
same in all scales.

Ruled lines across plans are: 6" apart in N 9" apart in TT 12" apart in HO


18" apart in S
24" apart in O
Exception:
Plan 34 has double
this spacing
See page 70 for
more data,


#### 33. Bayside & Southampton Ry. Very sharp curves




34. Laguna Plata RR. By R. S. Clark. Very sharp curves. Stub switches

#### 35. Denver & South Park RR. By Carroll Weis. Very sharp curves. Stub switches






36. Ft. Dodge & Elk City RR. Sharp curves. Easy construction




Railroads to 6 x 10

37. Yankee Midland Ry. Very sharp curves

By cutting a diagonal through the plywood table top and separating the surfaces, a channel is easily made so that some scenic features can be below track level.





Continued from page 4

get excellent scenic effects on almost any plan, so other factors like the routing of the main line may be more important in choosing a plan even though scenery is your chief interest.

In looking through the plans, you'll find most of them show suggestions for scenery. These ideas are not necessarily wedded to the particular plans on which you find them. You can treat any railroad with many different scenic themes equally well. Decide whether you want desert, mountain, prairie, rural, urban, industrial, timber, mining, waterfront or some other sort of scene without reference to your choice of a track plan. The chances are good that you can carry out your scenic theme on the track arrangement that is most convenient for other reasons.

#### Are level railroads easier to build than layouts with grades and bridges?

Yes, they're easier to build if you think only of getting track down. It's easy to slap down a sheet of plywood and lay either sectional or built-up track in place. I'd recommend one-level railroads for quick construction.

But you can miss much in the final scenic effect on a one-level railroad. The serious model railroader who wants a fine setting for his trains will be more satisfied if he has the time to

DAILY CITY

FAIRHAVEN

GILL CITY

GILL CITY

BENTON

ACADIA

38. Central Missouri RR. Sharp curves

#### 39. Denver & Northwestern RR. Conventional curves

The interesting features of this otherwise rather ordinary plan are the use of a lower (or, if you wish, upper) level for the branch, but with the rest of the railroad on a flat top. Also, the tracks allow for easy expansion of the main lines to the right and the eventual lengthening of yard tracks.

mensions and elevations by:

1/2" for N

1/4" for TT

1" for HO


11/4" for S


2" for O

Crossing angle is the

Multiply figured di-

Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.







#### 40. Troy & Mohawk Valley Ry. Above. Conventional curves

Loop-to-loop operation is something like the arrangement of a real railroad, yet it still permits you to run trains for a long time without stopping or backing. A control pit makes this railroad usable where some even smaller plans won't work.

#### 41. Quaker State Eastern RR. Below. Sharp curves

The river divides parallel lines as though they were either competing companies or a new and old route of the same company. It's best to build a river a few inches below track level.





Multiply figured dimensions and elevations by:

1/2" for N

3/" for TT


1" for HO

11/2" for S

2" for O

Crossing angle is the same in all scales.

Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.





#### 42. Sanaxis & Phrax RR. Sharp curves

The offset in track alignment, lower right, saves space. It allows the straight tracks to be closer together than could be permitted around sharp curves.

#### 43. Deadwood, Big Horn & Pacific RR. Sharp curves

Here's another one of those fascinating railroads that winds its way up a mountainside. Compare it with plans 34, 44, 63, 75, 78, 86, 95, and 96.







### Railroads up to 9 x 12

Fourteen plans

44. Rockport & South Fork Lumber Co. Sharp curves

I've been to several real places called Rockport and I think every one of them was a most interesting small seaport. Here a lumber mill ships its wares while a simple railroad brings timber down from the camp. Downhill trains go into a single-ended siding to let uphill trains go by.





46. Jordan Valley RR. Conventional curves

Here again a river helps to separate parallel tracks. On the left side the second line is hidden behind buildings.

Multiply figured dimensions and elevations by:

1/2" for N
3/" for TT
1" for HO
11/4" for S
2" for O
Crossing angle is the same in all scales.

Ruled lines across plan are

6" apart in N


9" apart in TT

12" apart in HO

18" apart in S

24" apart in O

See page 70 for more data.



47. Cerro Azul RR. By Charles Small. Sharp curves

This is one of my favorites of the switchback type of plan. Charles Small shows his knowledge of mining railroads and the influence of his experiences in South America in this plan, but it might be just as much at home in a Colorado or Idaho setting.

Continued from page 19

build a grid-type table with track at various levels. Books like Practical Guide to Model Railroading and Scenery for Model Railroads show how this is done; it's easier than you think once you actually start work.

Railroads that can be built an ane level: 3, 4, 10, 11, 12, 13, 16, 18, 19, 20, 21, 23, 25, 26, 31, 32, 36, 41, 55, 56, 68, 71, 72, 76 (first stage anly), 81, 83, 87, 89. Also, except for the branch line: 5, 39, 49, 69, and 91.

#### Will the curves handle all sizes of locomotives?

The curves for each plan are marked very sharp, sharp, conventional, or broad. Sharp curves are those commonly used with No. 4 track switches. Conventional curves are one third larger in radius and are usually used with No. 6 turnouts. Broad curves are at least a quarter larger, nearly double the radius of sharp curves.

You can run any kind of equipment on broad curves. Conventional curves will handle all but the largest locomotives. Passenger cars can be operated around conventional curves, but only shortened passenger cars will look right. Sharp curves will handle medium-sized locomotives and some large ones. Passenger cars don't look good on sharp curves. Very sharp curves are used on industrial lines, trolley layouts, and for tricky model railroads such as those built under a coffee-table glass. They usually require homemade or specially made switches. A very thorough discussion of curves can be found in the book Practical Guide to Model Railroading; this book also lists the radii that many commercially made locomotives can negotiate.

#### Aren't your turntables too small?

Could be. We have tried not to use big turntables on railroads where small locomotives are at home. But many model railroaders like big locos regardless. In most plans you can substitute almost any size of turntable for the one we show.

#### Are some plans better for my scale than others?

Whether in O, S, HO, TT, or N, the operation of any of these plans is the same. However, there is a difference because of the space you need to stand in, and the reach of your arm. In plan 93, there's a space next to the roundhouse where a fellow can stand to operate the main terminal and the


Continued on page 36

Ruled lines across plan are:

<sup>6&</sup>quot; apart in N 9" apart in TT

<sup>12&</sup>quot; apart in HO

<sup>18&</sup>quot; apart in S 24" apart in O See page 70 for more data.



48. Virginia & Truckee RR. Conventional curves

Much of the now abandoned and once fabulous V&T is recaptured here. The track arrangement could also fit well with other railroad themes. The conventional radius curves and No. 6 switches will take any locomotive. Some model railroaders will want to add a few more tracks in the two yards.

Multiply figured dimensions and elevations by:

'4" for N


"4" for TT

1" for HO

11/2" for S

2" for O

Crossing angle is the same in all scales.



49. Fairhaven & Ideal River RR. By Billi Bowen. Conventional curves. Custom switches

dullaply figured dimentions and elevations by:


\( \frac{N}{2} \) for N


\( \frac{N}{2} \) for TT

1° for HO

1% for S


Ruled lines across plan are
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O





50. Union & Overland RR. Sectional construction. Sharp curves

I once built a railroad in six pieces that bolted together to make a 10 x 12-foot layout. The plan of this was published and it became one of the top railroads in popularity. Along the same line of reasoning, I worked out this railroad with the idea of getting just as much operation into a smaller space. I have tried to include an adequate yard, scenic areas, interesting junctions, a crossing, and places to build factories on spurs. As on the original sectional plan, you can add more sections to fill a large space. See plan 61 for one possibility.



Multiply figured dimensions and elevations by:

15" for N

15" for TT


1" for HO

115" for S

2" for O


Crossing angle is the same in all scales.

Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.




52. Wisconsin Central RR. Conventional curves

In a square room, the arrangement of track is hampered by lack of distance between the corner curves. This plan makes the best of it with a twolap oval and a branch line.




53. New York, Ontario & Western RR. Sharp curves

The double-track oval serves as a mileage maker. Most of the operating interest will be in the yard and on the branch line.




54. San Marino & Echo Mountain Ry. Conventional curves

This is about the average of the sizes of model railroad actually built. Here a plan often used on a  $4 \times 8$  table is expanded to take a little more space.




55. Belfast & Moosehead Lake RR. By J. D. Latham Jr. Sharp curves and stub switches

This and plan 53 are based upon real railroads in the East. The B&ML is a line from a seaport to the main line of the Maine Central.



Multiply figured dimensions and elevations by: 1/2" for N 3/" for TT 1" for HO 11/2" for S 2" for O Crossing angle is the same in all scales.

Ruled lines across plan are: 6" apart in N 9" apart in TT 12" apart in HO 18" apart in S 24" apart in O See page 70 for more data.



56. Dayton & Northern RR. From a plan by H. F. Freeman. Broad curves

Here's a small railroad suited to the man who wants to test the largest locomotives and have a little operating fun as well.

### Railroads for 12 x 16 spaces


(Except plan 60 which is  $4\frac{1}{2} \times 11$ .)


57. Baltimore & Hudson RR. Conventional curves


58. Grand River Western RR. (Opposite page.) Conventional curves

a double-track oval. This plan became the most popular of all model track take a little less space, above, or a little more space, below. Notice that the main line is method explained on page 40. Notes in color show the changes that were made. This same idea is an easy way to The lower plan was developed from the upper by the seissors not level. This makes the loop grades much easier. return loops and a better yard to When the feature "Layout enlarge any other plan you plans. Here it is revised to

Crossing angle is the same all scales. Ruled three across plan are 6" apart in N
9" apart in Tr
12" apart in HO
18" apart in S
24" apart in S









#### 61. Dan Patch Lines. Sharp Curves

More yard capacity is provided in this plan than in the original from which it grew, plan 50. One advantage of building a railroad in sections is that you can build on the workbench where tools are handy. You can make alterations the same way even after the entire railroad is completed.




60. Platonica River Southern RR. Sharp curves but No. 6 switches

The ordinary effect of a simple oval is broken by putting the spurs at different elevations.



62. Adirondack RR. Conventional curves

Another popular plan from years ago. In one version it was called the "New York, New Haven & Hollywood." Besides offering a good main line, the branch increases the operating interest.



63. Rio Grande Southern Ry. Sharp curves. Stub switches

Probably more beautiful photos of a railroad scene have been taken near the Ophir Loop on the Rio Grande Southern than anywhere else in America. Now the real railroad is gone, but you can rebuild it in model form. This plan uses stub switches but No. 4 switches will fit with little or no change of track alignment. The left side of this railroad could be fitted into many other shapes of rooms by completely revising the right side.

Continued from page 24

engine terminal. This railroad was originally built in O gauge. If built in HO, the cockpit would be so small you couldn't stand in it. You need at least an 18"-square hole to stand in, and that's not big enough for a control panel too. The answer here, if you're working in a smaller scale, is to adjust things so you can build a larger control pit. You might have to move the roundhouse somewhere else or even omit it.

Most plans were designed with HO convenience in mind, so the S gauger and O gauger will have to look out for another hazard, that of having to reach too far from the edge of the table to get at some important place. Four feet is about as far as you can reach, and that's the limit. Look for a place to build another hatch for easier access or else move tracks around to make room for a hatch.

#### How do I choose a plan for an irregularly shaped space?

There are two good ways. The easiest way is to choose a plan that will fit into part of your space and then expand portions of the railroad into the extra areas. You do this by swinging one or several tracks sideways into the widened space, by moving a yard to an outside location (very likely an improvement), by swinging a track into an L or T so far that it makes a horseshoe or hairpin curve, by adding a branch line with many scenic industries, villages or resorts

Multiply figured dimensions and elevations by:

34" for N

16" for N

1" for HO

114" for S 2" for O

Ruled lines across plan are:

6" apart in N

9" apart in TT 12" apart in HO

18" apart in S

24" apart in O See page 70 for more data. along the new space, and so on. I'll give you more help on relocating track later.

The other way is to take a plan of about the proper area and bend it, stretch it, squeeze it or pinch it narrow at the middle. This takes more revising, but the method I'm going to describe of cutting a tracing of the plan into four corners and then relocating them is good for this.

#### More pointers about choosing your track plan

The most important thing to consider in making your choice is the arrangement of the main line. Is it long enough? Does it make an interesting journey for the trains?

Even though a particular plan doesn't have what you want in yards, scenery, spurs or other details, if the main line is right you've probably found the best layout for your needs.

Scenery can always be changed. In fact, you can treat almost any plan in

a thousand different ways when it comes to adding scenery.

Spurs can also be changed. You can add more, take some away, run others in different directions. Lots of fellows don't build spurs until later on anyway, and that's an idea that has some merit.

Passing sidings can also be moved. Likewise, you can change double track to single track or vice versa.

Yards aren't quite as flexible, but in almost any plan there are at least two places where yards could be located, so even here you have a choice. Look at yards on other plans; often you can make a substitution more to your liking.

We've tried to keep the yards in the plans to about the right sizes for the main lines they serve. However, most fellows eventually acquire more cars than they can use. If you're one of them, you'll either have to add more yard tracks somewhere, or else build a wall display case for extra equipment so the layout doesn't get yardheavy.


Many plans that have been published have wasted trackage that is added for effect without consideration of how trains will operate. One test of a good operating plan is that a train should go over practically all mainline track before repeating any of it. Alternate routes and cutoffs which connect into the main at two places usually are of little use and merely clutter up space. There sometimes are good reasons for having these cutoffs. but I'm criticizing plans that have a jumble of trackage that connects into itself here and there without ever really getting anywhere.

Branch lines are another thing. A branch line adds a lot of operating interest. Usually it works out best if it ties into the main line at only one place, at a point fairly well away from the main terminal. This makes for longer running.

# Check your aisles and operating spaces.

Many plans require some space outside the main tables for standing room.

Continued on page 68



Multiply figured dimensions and elevations by:

"" for N
"" for TT

1" for HO

11/2" for S

2" for O

Crossing angle is the same in all scales.

UNIONTOWN SPADES NORTON FISK CROSSING 0 BEL AIR

#### 64. Uniontown Southern RR. By Bill Wight. Broad curves

For two-train operation, this railroad has a serious flaw that can easily be corrected. As it stands, it's impossible to run two trains continuously in opposite directions as there is only one siding where they can pass (at Norton-East Bonnie). Any attempt to pass on the left half of the railroad is bound to send at least one train into the terminal. To correct this, a right-hand cross-over is needed between tracks two and three (counting inward), just to the left of the other cross-overs at Bel Air. Track three between this point and Walnut then becomes a second passing siding.

Continued from page 9


our location a bad choice, you can usually change the location of a yard to many other arrangements without changing much of the main line. The safest way to do this is to keep a yard attached to the main track at the same place, but swing it in another direction or build it on the other side of the main line.

To entirely relocate a yard, trace the plan without its yard. Then it will be easier to visualize all the new places where a yard can be built.

When you attach the yard to the main line at a new place, take a look at the return loops. In most plans the loops were located so you could get a maximum run before returning to the yard. To retain this feature, you'll have to move the place where the loops connect to the main line as well as the yard connecting point. We mentioned this long-run feature on page 3.


Factory spurs and other one-ended side tracks can be connected almost anywhere on any plan, so feel free to move them around, add more, take some away, etc. Keep in mind the limitation of cutting a No. 6 switch into a curve, as will be mentioned later.

Curves near the corners of the space and near other tracks are easily moved as long as you can still keep



Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.

38




the tracks from getting too close to each other or to the table edge.

A packet of tracing paper and a pencil can be used to combine parts of different plans quickly and safely. There's a track-planning template in the back of the book *Practical Guide to Model Railroading*. It can be a big help in replanning part or all of a plan. Another way is to trace parts of one plan in this book and then fit them to parts of another plan that uses the same radii and scale of drawing.

# How can I build a plan that's just a little too large for my space?

Can you build a drop leaf or removable section so that part of your railroad will be out of the way when not in use? If this won't work, you'll have to build the plan smaller. Sometimes you can move the corner curves inward and make new connecting tracks. This won't work on most plans for small spaces because we've already made the plans about as small as possible.

Changing to curves of a shorter radius saves a little space, but not as much as is often needed. If the plan has No. 6 switches, changing to No. 4 switches will save considerable space wherever switches are grouped. Building special switches with a curve all the way through them also saves space. Atlas Snap-Track switches Continued on next page



have a curve of this sort. You can use them in place of standard switch designs, but they won't help much unless you also lop off the extra 112" of straight track ahead of the points on these switches.

Building part of one switch overlapped into the space of the next is another way to save space. Slip switches and three-way switches are common forms of overlapped switches, but you can make many other unusual switches to save space.

Leaving out part of a plan also helps. Or you can change from double track to single track, omit an entire lap of the main line, leave out the roundhouse, etc.

#### How can I make the best use of extra space around the plan?

If your railroad space is bigger than the plan calls for, you're well off because almost any plan can be improved by a little expansion. Sometimes just leaving more space around the outer tracks is the best thing you can do. Tilting a plan diagonally in a space creates triangular corners for scenery and may improve an otherwise stiff-looking oval.

A very good way to expand a plan into a larger space is to make a tracing of the original plan, then cut through it each way. Paste the four corners you made into the corners of an outline drawing of your new larger space. Make new connections between the corners and your new expanded plan is done. Compare plan 57 with plan 58 for this is just what I did here.


If the plan you like has sharp curves and No. 4 switches, consider changing to conventional curves and No. 6 switches. This will take up a foot or so of your extra length and improve operation as well.

If your mainline has only two passing sidings, see if you can work in three by moving them around a little. Three is much better for two-train operation.

More yard trackage is always welcome. You can lengthen all yard tracks. If you need still more yardage, you can add more switches to the ladder or build another ladder on the other side of the main line. If you lengthen yard tracks, you may want to lengthen sidings as well as they must hold the same trains.


With quite a bit of extra space, you can consider adding a trolley line, a branch line, or perhaps an extra lap of main line for longer running.

One more way to enlarge a plan is to spread the whole railroad proportionately. Consider the squares as larger than originally intended. For



#### 67. Monon Route. Sharp curves

If you're familiar with the real Monon, you'll have fun with this plan. Otherwise you might want to use the track arrangement for some other theme. Some might want to use the Wabash River space to enlarge the yard.



68. Iron Ridge & Mayville. By Paul Larson. Conventional curves

Here's a honey of a point-to-point railroad for the fellow who wants to have the utmost in a realistic effect. The theme is a Milwaukee Road branch line.

Moin route

Other trock --Hidden trock

Optional route

Center of important curve

Turnout Pl---Frag

Elevations (Arrows point up grade)

fantal feeders
Letter R indicates separate reversing switch is needed.

Insulated gap both roils

Multiply figured dimensions and elevations by:

½" for N

¾" for TT

1" for HO

1½" for S

2" for O

Crossing angle is the same in all scales.

instance, in HO the squares might represent 15" instead of 12". This would make a railroad with curves of 25 per cent greater radii; the overall size of the plan would also be 25 per cent greater. Use the same size of track switch and figure switch locations by the P.I.F. method on page 7. Double track and yard tracks should not be spread when you use this method. Keep the original center-to-center distances.

#### Can I change a plan with a singletrack main line to double track?

This is fairly easy, but if your space is small you may need a few inches more in length and width than the original plan. Use the same curve centers and add a second track on the outside of the original mainline curves. If this pushes into the territory of another track, you'll have to move the next track out of the way.

This method will change the direction of straight trackage in reverse curves, which does no harm.

Compare plans 84 and 85. These are single-track and double-track versions of the same theme.

#### Can I substitute No. 8 switches for the No. 6 size shown in many plans?


Usually there isn't enough room for a substitution except in the biggest rooms. No. 8 switches take half again as much length as No. 6, and while they look nice they are not needed even for operating at speed.

# Can I add switches where the plans don't show them?

You can almost always cut a switch into an already existing straight track, but cutting a switch into a curve calls for a little caution. A regular No. 4 switch corresponds roughly to a radius a little larger than the curves it is usually used with (about 22" radius in HO for example). A No. 6 is a lot broader, however (about 48" radius in HO). So, particularly with a No. 6 switch, it's difficult and often impossible to cut a switch into an existing curve without introducing kinks that are just asking for car derailments. If you cannot relocate track centers to provide for a regular switch, build a custom switch with a curve through the frog.

Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.





#### 70. Springfield Electric Lines. Very sharp curves

At the two overpasses the upper track should be 4" above the lower (HO) and the grades connecting the upper and lower level should be uniform.

Ruled lines across plan are:

Plan 69 Plans 70, 71

6" apart in N 12" apart in N


9" apart in TT 18" apart in TT

12" apart in HO 24" apart in HO

18" apart in S 36" apart in S


24" apart in O 48" apart in O

See page 70 for more data.



#### 71. Hillsboro Traction Co. Very sharp

This electric railroad could be a real gem with the trolley wire well strung and the scenery nicely done. Putting the streets at an angle increases the apparent size of the space.



# 72. Charles City Western RR. Very sharp curves


Good industries along the line, plus interchange connections with three large railroads, have kept the real CCW going for years. Our plan is similar to the real track routes.

#### 73. Golden Key Route. Sharp curves

The "East Bay" cities along San Francisco Bay used to have a wonderful suburban service operated by competing companies. Much of the track was at street level and the automobile hampered the running of trains. Little of this is left today, but I've tried to recapture highlights in this composite system. The Berkeley street car has 7½" curves.


# Larger shelf railroads

for long narrow spaces



74. Nickel Plate System. Conventional curves


This two-lap oval should be easy to build and maintain. It can be improved by adding industrial switching spurs.




75. Thunderhead & Climax RR. Conventional curves

Here's another version of the switchback that works its way up a mountainside. This one provides rather large yards.


Other track - - --






77. Jamaica & Kingsway Short Line. Conventional curves with one sharp curve in the wye

This railroad is based on a very popular plan originally planned by Lt. Comdr. Ralph Butterfield for use in a single-car garage space.




78. Whitestone Cliffs Ry. Sharp curves

This one handles marble from a hilltop quarry to the pier. Future track at Mount Marpessa will allow up trains and down trains to pass. Note that this plan is drawn to a different scale.



79. Frisco Lines. Broad curves


This railroad makes more of the yard than most plans do. Even then it has plenty of room for industries, scenery, and space for the operator. Track-minded men may prefer the variation on page 46.




This is an expansion of a plan by Sanford D. Ashford, an authority on real railroad signaling. The layout furnishes interesting signaling problems and also provides junctions that will be fun to operate as a towerman. The man who likes railroadlike trackwork will also be happy with this type of model railroad.

# 81. San Diego & Arizona Eastern RR. Conventional curves with an exception

You'll have to make the table wider than four feet if you want to use 24" and 261/4" radii curves at Jacumba. Otherwise this railroad can handle any locomotive.







81. SD&AE. See opposite page


# Railroads for a single garage

82. Toledo & Southern Michigan RR. Conventional curves

The facilities of this road are so spread out that it could be used nicely for either club or home. Space along right side must be an aisle for operating.








Multiply figured dimensions and elevations by:

1/2" for N 1/4" for TT 1" for HO 11/2" for S 2" for O


Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O


See page 70 for more data.



#### 83. Yosemite Valley RR. Sharp curves


Once upon a time you could ride to the portals of wonderful Yosemite National Park through a glorious canyon along Merced River in the luxury of a fine observation car. One of the features along the line was an incline where timber was lowered to mainline level on flat cars held back by a cable. The cars had a bulkhead built at the lower end to keep the logs from sliding. The cable was at the side rather than between the rails. In Merced Yard, three-way and wye switches save space.





85. Ardmore, Cadosia & Fairmill RR. Broad curves except return loop

This two-track version changes the operation some because trains going in opposite directions need not make meets. Frequently we have named the stations on a railroad in alphabetical order. This is a help when you have visitors who want to help operate, but don't yet know your railroad thoroughly. A few other plans in this book are named in this way.



# 86. Cajon Pass, Salt Lake & Santa Fe RR. By John Armstrong. Conventional curves

Much of the transcontinental traffic to Los Angeles winds its way down steep Cajon Pass to San Bernardino. Both Santa Fe and Union Pacific share the track. Armstrong's plan features the rock outcroppings, the divided main line, and the interesting station at the bottom of the grade. Hardly any plan could be better to display your cars and locomotives.

Multiply figured dimenarions by:

Sign for N

We' for TT

I'm for HO


I'm' for HO

I'm' for S

Z'' for O

Crossing angle is the 24"


Ruled lines across plans are:
Plan 86 and 87
6" apart in N
12" apart in HO
18" apart in S
24" apart in O








#### 87. Pacific Great Eastern RR. Sharp curves


Only recently has the southern end (upper right) of the real PGE been extended to reach the city of Vancouver, B.C. We show the line as it used to be, getting passengers by boat and freight cars by car float. The parts on each side of the central back-drop could be turned in other directions to make an L or else an around-the-wall type of plan.














# 91. Opposite page. Toledo & Indiana RR. Display railroad with broad curves

This railroad was planned for a museum with the special problems of operation and maintenance kept in mind. The central area is a hidden repair shop. At the upper right are holding tracks so alternate trains can be operated. The branch can be operated by a switcher shunting from mine to industry without reaching the mainline tracks.

Multiply figured dimensions
and elevations by:

1/2" for N


3/4" for TT


1" for HO

11/2" for S

2" for O

Crossing angle is the same in all scales.





#### 92. Opposite page. Missouri-Kansas-Texas System. Conventional curves

This is really two railroads. The steam-diesel system with a big yard and hidden loops and holding tracks, as well as one line that stays in sight around the room, is one system. Connecting to it at Tulsa is an electric industrial line. (Maybe it takes passengers too.) This winds down from a gravel pit to the main street. It must switch back twice to reach the interchange with the big railroad.

Ruled lines across plan are:
6" apart in N
9" apart in TT
12" apart in HO
18" apart in S
24" apart in O
See page 70 for more data.


#### 93. Tennessee Eastern Ry. Broad curves


MADISON

This railroad was designed for the Children's Museum in Nashville, Tenn., and the O gauge club of Nashville built and operate it.

HARTSVILLE

CARTHAGE







Estate-size railroad

### If I had a million


What kind of a railroad would you build if given unlimited funds?



This section through the roilroad room shows the three kinds of lighting that combine to make a sun-ond-clouds effect. The ceiling is white so that colors other than blue can be played on the sky.



Club-size railroad



WHEN money and space are no problem in building a railroad, there are still practical limitations such as determining just what size it will be and the method of planning it. This railroad isn't impossibly big, at least for a club, for as this is written a version of it is well under way at the HO club in the B&O station at Wheeling, W. Va.

A super railroad should be big enough to keep a man busy at his hobby of building, operating and rebuilding. It shouldn't be so large, however, that maintenance takes up more time than construction. Here are some of the ideas incorporated into this plan:

The building is designed specifically to house the railroad. A ground floor entrance, workshop, storage space and lounging area are provided, convenient to the layout. A balcony provides bird's eye viewing and an operating position for mainline track running. Switching and way freights are handled while walking alongside the trains.

The aisles are arranged radially so you can either stand at one point and see all of the railroad, or you can walk into one bay to get a realistic view of just one scene.


A room 60 x 65 feet is best for this railroad in HO, but similar arrangements can be worked into spaces of 50 feet, or perhaps less. The railroad room needs no windows; in fact, it shouldn't have them, but good dust-proof ventilation or air conditioning is desirable. Lighting consists of even "sky light" reflected from a curved false ceiling. Holes through the ceiling allow yellowish spot lights to send

beams of "sunlight" down as though from openings between clouds. All spotlights are pointed at the same downward angle and their beams do not overlap.


The railroad itself must be a plan that looks like a possible, if not entirely probable, scene in any close-up view. Loop-to-loop operation is almost essential unless there's going to be plenty of manpower available to switch trains in the terminals. Naturally, switching is wanted, but it's hard to keep the main line busy if all trains must be turned in a yard. The loops let many trains turn easily.


Track doesn't ever return into the same scene twice except to climb to the summit.

Angels' Fleight is a funicular (cable railroad) to a pagoda and amusement park atop Blackwall Palisade.










# ORRVILLE WEST ORRVILLE Jumper-feeders to 5 rails only

#### 96. Orrville Mining RR. Sharp curves

Hidden tracks allow mainline trains to serve Orrville from both directions. Two mainline trains can be used, one headed each way. After leaving Orrville in either direction, they back into their storage sidings inside the mountain. Of course, the important operation here is the branch line to the mine.




#### 97. Philadelphia & Reading System. Broad curves


Parts of this plan came from another railroad that I designed for George Allen. This is a real "bowl of spaghetti" type of plan and should appeal to the man who wants a really long main line and interesting routing in a compact area. Suburban trains operate from overhead catenary over part of the line, then they take a short cut back to the terminal. A suspended car on a cable rises to the summit of the mountain on the hour. Notice the short and long routes between Mahanoy Junction and Port Clinton Junction. At Wayne Junction some slip switches are needed both for looks and to save space.


> Multiply figured dimensions and elevations by: for N for TT for HO 12 for S 2" for O Crossing angle is the same in all scales.

Ruled lines across plan are: 6" apart in N 9" apart in TT 12" apart in HO 18" apart in S 24" apart in O See page 70 for more data.

PHILADELPHIA







South Bend, South Shore & Chicago RR. Broad curves

planned around features

train movements

Continued from page 8


interfere with operations, so be sure you know what you are doing.

#### How about feeders?

Move them to any convenient place along the very same rail, but not beyond any gaps in the rails.

# What do I do when the letter R appears near track feeders?


Eventually you'll want to build a control panel such as the dual-throttle type on page 57 of the book *How to Wire Your Model Railroad*, but at first you can get by with only one extra reversing switch of the double-pole double-throw type.



Connect all mainline tracks through this switch. Connect R feeders direct to your regular controls, bypassing the new direction-control switch.


#### How are crossings wired?

Our plans are wired with the assumption that all crossings have jumpered wiring. This is the way most, if not all, commercial crossings are made.



#### How about scissors or double crossovers?

Most commercially made crossovers don't have enough gaps for proper two-train operation. There should be no way for electricity to get from one approach of the crossover to any other. Usually you must cut your own gaps at XX in addition to those ready made.



You certainly want to reach the switches of a yard from a convenient aisle. All small plans present this problem, and you should keep it in mind when looking for a suitable one. Larger plans usually provide operating aisles within the table space.

If one side of the railroad must be tight against a wall, either choose a side that has few if any switches, or else provide 18"-square hatches where you can pop up through the scenery to get at them.

If your room is large enough, try to provide an 18" aisle behind all parts of the railroad and a 36" or wider aisle wherever visitors will want to go; 24" is enough for one-man control spaces.

# Do many of these plans seem too complicated?

We've put a lot of detail into our plans to help you with construction. This makes them look much more complex than if you saw just the track lines alone. But if the plans for your size of space still have more in them than you want, choose a plan for a smaller space and build it instead. You can easily blow any plan up to a larger size by methods explained on page 5.


Don't overlook the idea of building plans as simple as those on page 2 into spaces two or more times as big.


## 100. Ohio Central System. Conventional curves


This plan is quite adaptable to variations both in scenic treatment and in the routing of main lines. The terminal is easily accessible. Black Hand Gorge is a real place, near Newark, Ohio, where an old canal towpath in ruins skirts the river. The nearby tunnel was for an interurban line, but I've used it for the steam-diesel road instead.


Euclid Shops

CUYAHOGA









# PLAN INDEX

Arrangement: Plans are listed in same order as in the main part of this book. They are in order of size, but with a number of exceptions.

Plan size: is to the nearest foot in each scale.

Curve radii: are for curves limiting mainline operations.

Turnout size: Most plans use No. 4 or No. 6 track switches and exceptions are marked on the plan. If you don't care to build stub

or custom switches, which usually aren't ready-made, you can often substitute No. 4 turnouts without any major changes.

Grades: are shown to nearest half per cent. These are a general guide as to how heavy a locomotive is needed to pull a given train. Grades are deliberately made stiffer than need be on some plans for visual effect.

Space shape: "Table" means two or more sides must be accessible for maintenance. "Front aisle" means other sides may be against walls. "Central aisle" reaches into

space from outside: no ducking. "Open center" must be reached by ducking or via stairway. "Shelt" is narrow and usually can be bent around corners. See plan 94 for explanation of "radial aisle."

Operating pattern: "Oval" means any continuous route where track is not redoubled. Includes figure-eights, etc. "Return" means a loop or track which reverses direction of train one-way around oval. "Returns" allow reversal both ways. "Point" is a stub terminal. "Loop" is a return loop with or without a stub yard in conjunction with it. "Combination routing" is a particularly flexible arrangement consisting of a terminal-to-loop route using most if not all the main line available. In addition there are connecting tracks for oval running and returning in each direction around the oval. On some larger plans exact descriptions can't be made in the space of this index.

FOR	N SCALE	RAILRO	DADS, DI	VIDE THE	HO D	IMEN	SIONS	BY 2	No.	e ent		
Plan No.	TTW	idth and	length in	feet o			mainlin n inches S		Turnout frog No.	Mainline grade per cent	Plan No.	Name. space, operating scheme.
1	2×3	3×4	4x6	6×8	1114	15	2212	30	4	41/2	1	Stockton & Darlington RR. Table. Twa-lap oval. Small yard.
2	3×3	3×4	5×6	7×7	11%	15	2212	30	4	41/2	2	Kettle Hills & Eastern RR. Table. Twa-lap aval.
3	3×3	4×5	6×7	8×10	131/2	18	27	36	4		3	Bay State Western Ry. Table. Dauble-track aval.
4	3×4	4×6	6×9	8×12	131/2	18	27	36	4		4	Reddy River & Piedras RR. Table. Oval with raundhause.
5	20×29	26×38	39×57	52×76	18	24	36	48	6		5	Atlantic Air Line, U-shelf. Laap ta laap. Easy grades along shareline.
6	1×5	1×6	2×9	3×12	131/2	18	27	36	4		6	Switchman's Nightmare. Shelf. Yard anly.
7	1×3	1×4	2×6	2×8	18	24	36	48	6		7	Apple Creek Junction Ry. Shelf. Yard anly.
8	1×12	1×16	2×24	2×32	131/2	18	27	36	4	4	8	Port Ogden & Northern RR. Shelf. Yards and switchback.
9	14×29	19×39	29×58	38×77	221/2	30	45	60	6	21/2	9	Erie RR. Shelf and central aisle. Camplete system. Large yard.
10	2×5	3×6	5×9	6×12	1114	15	2212	30	4		10	Pittsburgh, Midvale & Ironton RR. Table. Yard to industry.
11	3×4	4×5	5×8	7×10	18	24	36	48	6		11	Logan Square Yard. Carner shelf. Yard.
12	2×6	2×8	3×12	4×16	18	24	36	48	6		12	Mechanic Street Yard, Shelf, Yard,
13	3×5	3×7	5×10	6×14	131/2	18	27	36	4		13	Elizabeth & Rahway Valley Ry. Table or front aisle. Oval with return.
14	3×5	4×7	6×10	8×13	131/2	18	27	36	4	4	14	Blue Valley RR. Table ar frant aisle. Oval:
15	3×4	5×5	7×8	9×10	131/2	18	27	36	4	4	15	Lake District Ry. Table. Three-lap aval.
16	3×5	4×6	5×9	7×13	111/4	15	221/2	30	4		16	Valley Central Lines. Table. Oval.
17	3×5	4×7	5×10	7×13	11%	15	221/2	30	4	41/2	17	Gorre & Daphetid RR. Front aisle ar table. Twa-lap aval and branch.
18	3×5	4×7	6×10	8×13	131/2	18	27	36	4		18	Turtle River Industrial District. Frant aisle ar table. Oval.
19	3×5	4×6	5×9	7×13	1312	18	27	36	4		19	Dwight & Pontiac RR. Table. Oval. Shelf extension is extra width.
20	3×5	4×7	6×11	8×14	131/2	18	27	36	4		20	New Industry Connecting RR. Table. Oval. Switching featured.
21	3×4	4×5	6×8	8×10	131/2	18	27	36	4		21	Rockport & Oyster Bay Ry. Front aisle. Oval.
22	3x4	4×6	6x9	8×12	131/2	18	27	36	4	31/2	22	Tonopah & Salt Range RR. Table. Twa-lap aval.
23	3×4	4×5	6×7	8×19	131/2	18	27	36	4		23	Columbia & Cascade RR. Table. Oval.
24	3×6	4×8	6×12	8x16	1312	18	27	36	4	4	24	Toronto, Hamilton & Detroit RR. Table. Cambinatian rauting.
25	3×6	4x8	6×12	8x16	131/2	18	27	36	4		25	Mohawk Southern Ry. Table. Oval.
26	3×6	4×8	6×12	8×16	131/2	18	27	36	4		26	Pennsylvania & Potomac RR. Table. Oval and paint to paint.
27	3×6	4×8	6×12	8×16	1312	18	27	36	4	31/2	27	Tremont & Cambridge RR. Table. Oval and terminal ta laap.
28	3×6	4×8	6×12	8x16	1312	18	27	36	4	31/2	28	Rock Island & Moline Belt Line. Table. Laap ta laap and aval.
29	3×6	4×8	6×12	8×16	131/2	18	27	36	4	4	29	Nantahala & Smoky Mountain Gorge RR. Frant aisle ar table. Two-

lap aval.

30 Lime Ridge, Hercules & Portland RR. Table. Twa-lap oval.

30

3x6

6x12

8x16

1114 15

221/2 30

FOR N SCALE RAILROADS, DIVIDE THE HO DIMENSIONS BY 2 32												
Plan	width and length in feet					imum	mainlin inches S	e	Turno frog 7	Mainline grade per cent	Plan No.	Name, space, operating scheme.
No. 31	3×6	4×8	6×12		111/4	(15.5)	221/2	2000	4		31	Jersey Valley Central RR. Table or shelf. Twa-lap aval.
32	3×6	4×8	6×12	8×16	111/4		221/2		4		32	Custer & Frant Range RR. Table. Oval.
33	3x6	4x8	6×12	8×16	1114		221/2	200	4	4	33	Bayside & Sauthamptan Ry. Frant aisle. Two-lap oval.
34	3×6	4x8	6×12	8×16	111/4		221/2		Stub	41/2	34	Laguna Plata RR. Front aisle. Paint to paint and aval.
200					93/4		191/2	Callery .	Stub	51/2	35	Denver & South Park RR. Table. Oval with returns.
35	3×6	4x8	6×12	8×16			27		207	372		
36	3×6	4×8	6×12		131/2			36	4	21/	36	
37	3×6	5x9		11×15	12	16	24	32	4	31/2	37	Yankee Midland Ry. Table. Oval.
38	4x3	6×6	8×9	11×12	131/2		27	36	4	31/2	38	Central Missauri RR. Twa-lap aval.
39	4×8	5×10	8×15	- CONTRACTOR (CO.)	18	24	36	48	6	•	39	Denver & Narthwestern RR. Table. Oval.
40	5×8	6×10	9×15		18	24	36	48	6	2	40	Tray & Mahawk Valley Ry. Open center. Laap ta laap.
41	5×7	6×9	9×14		131/2		27	36	4		41	Quaker State Eastern RR. Open center. Oval with alternate route.
42	5×5	6x7	8×11	11x14	131/2		27	36	4	31/2	42	Sanaxis & Phrax RR. Open center. Twa-lap aval and return.
43	5×6	6×8	8×12	11×16	131/2		27	36	4	31/2	43	Deadward, Big Harn & Pacific RR. Table. Loap to laop. Mining.
44	3×6	5x7	7x11	9×14	13½	18	27	36	4	4	44	Rackpart & Sauth Fark Lumber Ca. Table. Point to point. Lumber.  Grade aptianal.
45	6×8	8×10	12×15	16×20	131/2	18	27	36	6	4	45	Superiar & Iran Range RR, Central aisle, Point ta paint. Ore.
46	6×9	8×12	12×18	16×24	18	24	36	48	6	3	46	Jordan Valley RR. Central aisle. Ovals.
47	4×9	5×12	8×18	10×24	131/2	18	27	36	4	31/2	47	Cerra Azul RR. Table. Switchback. Elaborate yard.
48	7×9	9×12	14×18	18×24	18	24	36	48	6	31/2	48	Virginia & Truckee RR. Central aisle. Paint to point and aval. Old time.
49	6×8	9x11	13×16	17×21	18	24	36	48	Custom		49	Fairhaven & Ideal River RR. Display table, Oval with branch.
50	5×9	7×12	11×18	14×23	131/2	18	27	36	4	4	50	Union & Overland RR. Open center. Paint to laap and aval. Sectional frame.
51	6×9	8×12	11×18	15×23	131/2	18	27	36	4		51	Chicaga Inner Belt Line. L-shelf. Yards and industries.
52	6×6	8×8	12×12	16x16	18	24	36	48	6	2	52	Wiscansin Central RR. Open center. Two-lap aval and branch.
53	7×9	9×12	14×18	18×24	131/2	18	27	36	4	3	53	New Yark, Ontario & Western RR. Open center. Oval with branch fram wye to laap.
54	5×8	6×11	9×17	12×22	18	24	36	48	6	3	54	San Marina & Echa Mauntain Ry. Frant aisle and open center. Cambinatian rauting.
55	7×8	9×11	14×16	18×21	131/2	18	27	36	Stub		55	Belfast & Moasehead Lake RR. U-shelf. Paint to paint.
56	5×9	6×12	9×18	12×24	221/2	30	45	60	6		56	Daytan & Narthern RR. Open center, Oval.
57	5×8	7×10	11×15	14×20	18	24	36	48	6	21/2	57	Baltimare & Hudsan RR. Frant aisle and apen center. Oval with returns. Papular.
58	7×9	10×13	15×17	20×26	18	24	36	48	6	21/2	58	Grand River Western RR. Enlarged version of plan 57.
59	8×9	10×12	15×18	20×24	18	24	36	48	6	3	59	Great North Pass RR. Frant aisle. Cambination rauting.
60	3×8	5×11	7×17	9×22	131/2	18	27	36	6	2	60	Platanica River Sauthern RR. Table. Oval. Large yard.
61	5×11	7x15	11×23	14x30	131/2	18	27	36	6	4	61	Dan Patch Lines. Enlarged version of plan 50.
62	9×9	12×12	18×18	24×24	18	24	36	48	6	2	62	Adirondack RR. Central aisle. Laap ta loap, aval, and branch. Yard.
63	8×11	11×14	17×21	22×28	131/2	18	27	36	Stub	4	63	Ria Grande Sauthern Ry. Central aisle. Point to point and aval.
64	8×11	10×15	15×23	20×30	18	24	36	48	6	3	64	Uniantawn Sauthern RR. Open center. Oval with return.
65	7×11	9×14	14×21	18×28	18	24	36	48	6	3	65	Southern Crass Ry. Ca. L-shaped. Oval with returns and branch. Yard.
66	7×11	9×14	14×21	19×28	21	28	42	56	6	3	66	Eureka, Shasta & Great Eastern Ry. L-shaped. Paint to laap and aval.
67	7×10	10×14	14×20	19×27	131/2	18	27	36	4	31/2	67	Monan Route. Central aisle. Oval and returns.
68	9×12	12×16	18×24	24x32	18	24	36	48	4		68	Iran Ridge & Mayville RR. U-shelf. Point to point.

1/2" scale

Us


ω

	FOR	N SCALE	RAILRO	ADS DI	VIDE THE	HO D	MENS	IONS	BY 2	100	unline ide cent		
	Plan			length in		Mini	mum n	nainlin		Turno frog N	Maini grade per ce	Plan No.	Name, space, operating scheme.
%" scole	No.			21×31		51/2	71/2	11	15	Custom		69	Union Bay Transit, Central aisle. Trolley routes. 7 per cent grade
61)		1000							0.4		: #177	70	on branch.
	70	4×7	5×9	8×14	10×18	9	12	18	24	Custom	51/2	70	Springfield Electric Lines. Table. Trolley routes.
	71	4×7	5×9	8×14	10×18	634	9	131/2	1650	Custom		71	Hillsboro Traction Co. Table, Trolley oval.
	72	3×14	4×18	6×27	8x36	674	9	131/2	1165	Custom		72	Charles City Western RR. Shelf. Point to point and oval trolley.
	73	8×15	10×20	15×30	20×40	131/2	18	27	36	4	4	73	Golden Key Route. Open center. Suburban electric routes. Steam shuttle.
	74	5x12	6×16	9×23	12×31	18	24	36	48	6	21/2	74	Nickel Plate System. Open center. Two-lap oval. Large yard.
	75	4×11	5×15	8×23	11×30	18	24	36	48	6	3	75	Thunderhead & Climax RR. Shelf. Switchback.
	76	5×8	7×11	11×16	14x21	18	24	36	48	6	3	76	Ouachita & Ozark RR. Open center with shelf extension. Two-lap oval.
	77	4×14	5×18	8×27	11×36	18	24	36	48	6	2	77	Jamaica & Kingsway Short Line. Table. Combination routing.
	78	2×9	3×12	5×18	6×24	131/2	18	27	36	4	5	78	Whitestone Cliffs Ry. Shelf. Switchback from quarry to wharf.
	79	6×14	9×19	13×28	17×38	221/2	30	45	60	6	2	79	Frisco Lines. Open center. Two-lap oval. Large yard.
	80	5×11	7×15	10×22	13×30	18	24	36	48	6	31/2	80	East Bay Belt Line. Front aisle and open center. Ovals and returns.
	81	3×15	4×20	6×30	8×40	131/2	18	27	36	6		81	San Diego & Arizona Eastern RR. Shelf. Terminal to loop.
	82	7×15	9×21	14×31	18×41	18	24	36	48	6		82	Toledo & Southern Michigan RR. Front aisle and open center. Loop to loop plus branch. Easy grades.
	83	8×13	10×18	15×26	20×36	131/2	18	27	36	4	21/2	83	Yosemite Valley RR. Central aisle. Point to point. Could be one- level.
	84	8x15	10×20	15x30	20×40	221/2	30	45	60	6	2	84	The Wiscona Route. Open center. Combination routing.
	85	8x14	10x19	15×28	20×37	221/2	30	45	60	6	2	85	Ardmore, Cadosia & Fairmill RR. Variation of plan 84.
	86	8×15	10×20	15×30	20×40	18	24	36	48	Mixed	3	86	Cajon Pass, Salt Lake & Santa Fe RR. Open center. Loop to loop and oval.
	87	8×14	10×18	15×27	20×36	131/2	18	27	36	4	4	87	Pacific Great Eastern RR. Table. Point to point. Could be one-level.
	88	11×15	15×20	23×30	30×40	18	24	36	48	4,6	3	88	Chesapeake & Ohio RR. Front and central aisle. Point to point and oval.
	89	10×15	14×20	20×30	37×39	18	24	36	48	6		89	Bednigo & Pine River RR. Open center. Terminal to loop and oval.
	90	9×15	12×21	18×31	24×41	221/2	30	45	60	6	2	90	Atlanta, Birmingham & Columbus RR. L-shaped. Combination routing.
	91	11×12	15×16	23×25	30×33	27	36	54	72	6		91	Toledo & Indiana RR. Display case. Oval. Central workshop.
	92	9x14	12×19	18×29	25×33	18	24	36	48	6	2	92	Missouri-Kansas-Texas System. Open center. Ovals and returns.  Trolley branch.
	93	11×17	14×23	21x35	28×45	221/2	30	45	60	6	2	93	Tennessee Eastern Ry. T-table. Oval with return. Wye and terminal.
	94	40×45	53×60	80×90	106×120	27	36	54	72	8	112	94	Eureka & Golden Gate RR. Radial aisle. Loop to loop. Idea plan.
	95	11×28	14x38	21×57	28×76	131/2	18	27	36	4	4	95	Hungry Horse Timber Co. Radial aisle. Point to point with loops.
	96	2×15	3×20	5×30	6×40	12	16	24	32	6	4	96	Orrville Mining RR. Shelf. Switchback.
	97	9×20	12×26	18×39	24×52	221/2	30	45	60	6	3	97	Philadelphia & Reading System. Table. Combination routing. Complex.
	98	11×13	14×17	21×25	28×34	18	24	36	48	6	2	98	Butte, Anaconda & Pacific RR. Central aisles. Point to point and oval.
	99	35×40	47×53	70×80	94×106	Vario	ous br	oad re	adii.	6	2	99	South Bend, South Shore & Chicago RR. Central aisle table. Complete railroad.
scole	100	12×14	16×19	24×29	32×38	18	24	36	48	6	2	100	Ohio Central Lines. L-shaped. Combination routing.
3/16" \$	101	2000000			40×40	18	24	36	48	6	4	101	White Pass & Yukon Ry. Central aisle. Point to point.
							1355	10000	98.5			101	Time rass a roken ky. Central dister contrib point.
	72	1											

8 7

| | 0 1 2 3 4 5 6 7 8 9 10 1/1 1/2 1/3 1/4 1/5 1/6 1/7 1/8 1/9 2/0 2/1 2/2 2/3 2/4 | 1/8 1/7 1/6 1/3 1/2 1/1 1/0


















# These Kalmbach books are available for your railroad reference library.

No longer the property of the

Boston Public Library.

THE TRAIN-WATCHER'S GUIDE TO CAN RAILROADS offers information o railroads, including a brief history, yard Sale of this material benefits the Lib. - Tyradio frequencies used. 180 photos. \$10.!

THE HISTORICAL GUIDE TO NO RAILROADS is your ticket to railroad comprehensive coverage of more than abandoned since 1930. 376 pages! \$20.

AMERICAN SHORTLINE RAILWA to America's fascinating and diverse sn facts (such as enginehouse locations a

figures, and rosters for 400 short lines!

DIESEL LOCOMOTIVE ROSTERS MEXICO is a new, 168-page 2nd edition rosters for more than 350 railroads. In 1's, short lines, even military units! \$9.

Sale of this materia BRANCH

> 89007296-27 CD

The Date Due Card in the pocket indicates the date on or before which this book should be returned to the Library.

pocket.

'ER'S GUIDE is the definduction from the first dieires of diesels are covered, strated pages. \$15.95

ADS AND RAILROAD to over 200 tourist lines ludes how-to-get-there in-

E: THE STORY OF **IVES** recalls the diesels Centipedes to Sharks! 152 uction list! \$18.95

D TO ABDICATE AND gan's and Philip R. Hasrmance of steam. Travel pages, 431 photos. \$25

Please do not remove cards from this

cent sales tax.

C Kalmbach Publishing Co.

When ordering direct, include po

Prices subject to change

# 101 TRACK PLANS FOR MODEL RAILROADERS

Every one of the 101 track plans in this book is an adventure in model railroad design — a complete miniature world with a theme, purpose, and atmosphere. The plans range in size from tiny layouts that would fit on a card table to a huge estate-size railroad designed for a specially built building. The author, Linn Westcott, also explains how to convert the plans for use in the various model railroad scales, how to build a layout from a plan, and how to choose the plan best suited to your space and personality.

GUNLOCK JC

KALMBACH BOOKS